TCP
Sliding Windows, Flow Control, and Congestion Control

Based on

Peterson and Davie Textbook

Sliding Windows

- Normally a data link layer concept
- Interest is understanding TCP mechanism at the transport layer.
- Each frame is assigned a sequence number - SeqNum
- The sender maintains three variables: send window size (SWS), last ACK received (LAR), and last Frame sent (LFS)

Sender Variables

- SWS :: the upper bound on the number of outstanding frames (not ACKed) the sender can transmit
- LAR :: the sequence number of the last ACK received
- LFS :: the sequence number of the last frame sent

Sender Invariant

LFS – LAR <= SWS



Sender Window

- An arriving ACK ➔ LAR moves right 1

  ➔ sender can send one more frame
- Associate a *timer* with each frame the sender transmits
- Sender retransmits the frame if the timer *times out*
- Sender buffer :: up to SWS frames

Receiver variables

- Receiver window size (RWS) :: the upper bound on the number of out-of-order frames the receiver is willing to accept
- Largest acceptable frame (LAF) :: the sequence number of the largest acceptable frame
- Last frame received (LFR) :: the sequence number of the last frame received

Receiver Invariant

LAF – LFR <= RWS



Receiver Window

When a frame arrives with SeqNum:

If (SeqNum <= LFR or SeqNum > LAF)

the frame is ***discarded*** *because it is outside the window.*

If (LFR < SeqNum <= LAF)

the frame is ***accepted****.*

Receiver ACK Decisions

SeqNumToAck :: largest sequence number **not yet ACKed** such that all frames <= SeqNumToAck have been received.

- Receiver ACKs receipt of SeqNumToAck

  and sets

  LFR = SeqNumToAck

  LAF = LFR + RWS

SeqNumToAck is adjusted appropriately!

TCP Sliding Windows

* *switch from packet pointers to byte pointers*

- Guarantees reliable delivery of data.
- Ensures data delivered in order.
- Enforces flow control between sender and receiver.
- The idea is: the sender does not overrun the receiver's buffer.

Receiver's Advertised Window

- The big difference is that the size of the sliding window size at the receiver is not fixed.
- The receiver *advertises* an adjustable window size (AdvertisedWindow field in TCP header).
- Sender is limited to having no more than AdvertisedWindow bytes of unACKed data at any time.

TCP Flow Control

- The discussion is similar to the previous sliding window mechanism except we add the complexity of sending and receiving *application processes* that are filling and emptying their local buffers.
- Also we introduce the complexity that buffers are of finite size without worrying about where the buffers are stored.

MaxSendBuffer

MaxRcvBuffer

TCP Flow Control

- Receiver throttles sender by advertising a window size no larger than the amount it can buffer.

On TCP receiver side:

LastByteRcvd - LastByteRead <= MaxRcvBuffer

to avoid buffer overflow!

TCP Flow Control

TCP receiver advertises:

AdvertisedWindow = MaxRcvBuffer - (LastByteRcvd - LastByteRead)

i.e., the amount of free space available in the receiver's buffer.

TCP Flow Control

The TCP sender must adhere to AdvertisedWindow from the receiver such that

LastByteSent – LastByteAcked <= AdvertisedWindow

or use EffectiveWindow:

EffectiveWindow = AdvertisedWindow – (LastByteSent – LastByteAcked)

TCP Flow Control

Sender Flow Control Rules:

1. EffectiveWindow > 0 *for sender to send more data*
2. LastByteWritten – LastByteAcked <= MaxSendBuffer

   equality ➔ *send buffer is full!!*

   ➔ *TCP sender process must* ***block*** *the sender application.*

TCP Congestion Control

- CongestionWindow :: a variable held by source for each connection.

* TCP is modified such that the maximum number of bytes of unacknowledged data allowed is the *minimum of* CongestionWindow and AdvertisedWindow.

MaxWindow :: min (CongestionWindow , AdvertisedWindow)

TCP Congestion Control

And finally, we have:

EffectiveWindow = MaxWindow – (LastByteSent – LastByteAcked)

The idea :: the source's effective window can be **no faster** than the slowest of the network (i.e., its core *routers*) or the destination Host.

* *The TCP source receives implicit and/or explicit indications of congestion by which to reduce the size of* ***CongestionWindow.***